

# Cabled MP3 Player Pouch



www.pandayarns.biz



## MEASUREMENTS

Pouch measures:  
Length: 10 cm  
Width: 6 cm



intermediate  
knitting

## MATERIALS

**Panda Woolbale 8ply** (50g balls)  
Quantity 1  
One pair of 4.00mm knitting needles and a set of **double pointed** 4.00mm knitting needles or THE REQUIRED SIZE TO GIVE CORRECT TENSION; a 4.00mm crochet hook; small amount of contrast yarn; cable needle; 1 stitch holder; 2 buttons; wool needle for sewing seams.

## TENSION

This handknit has been designed at a tension of 22 sts and 30 rows to 10cm over stocking st, using 4.00mm needles.

## ABBREVIATIONS

**beg** = begin/ning; **cm** = centimetres; **ch** = chain; **cont** = continue; **inc** = increase, increasing; **incl** = inclusive, including; **K** = knit; **P** = purl; **patt** = pattern; **rep** = repeat; **sl** = slip; **st/s** = stitch/es; **stocking st** = knit right side rows, purl wrong side rows; **tog** = together; **yon** = yarn over needle – take yarn over top of needle into knitting position, making a st; **yrn** = yarn round needle – take yarn right around needle into purling position, making a st.

## SPECIAL ABBREVIATIONS

**'C4F'** = slip next 2 sts onto cable needle and hold at front of work, K2 from left-hand needle, then K2 from cable needle.

**'C4B'** = slip next 2 sts onto cable needle and hold at back of work, K2 from left-hand needle, then K2 from cable needle.

## POCKET LINING

Using a pair of 4.00mm needles, cast on 12 sts.  
Work 16 rows stocking st.

**17th Row:** \* K2, inc in next st, rep from \* to end ... 16 sts.

**18th Row:** K1, P2, K2, P6, K2, P2, K1.

**19th Row:** P1, K2, P2, K6, P2, K2, P1.

Leave sts on a stitch holder.

## POUCH

**NOTE:** The crochet cast-on which starts the pouch is temporary. After completing the work, it will be unpicked. The sts are then cast off tog.

Using a 4.00mm hook and contrast yarn, make approx 39ch.  
Using a set of 4.00mm needles and working yarn, beg 2ch in from end, knit up 32 sts, working into the back of each ch.

**1st Round:** P1, K2, P2, K6, (P2, K2) twice, P2, K6, P2, K2, P1.

**2nd Round:** As 1st round.

**Beg Patt:**

**1st Round:** P1, K2, P2, K2, 'C4F', (P2, K2) 3 times, 'C4F', P2, K2, P1.

**2nd Round:** P1, K2, P2, K6, (P2, K2) twice, P2, K6, P2, K2, P1.

**3rd and 4th Rounds:** As 2nd round.

**5th and 6th Rounds:** As 1st and 2nd rounds.

**7th Round:** P1, K2, P2, 'C4B', (K2, P2) 3 times, 'C4B', K2, P2, K2, P1.

**8th, 9th and 10th Rounds:** As 2nd round.

**11th Round:** As 7th round.

**12th Round:** As 2nd round.

Last 12 rounds form patt.

Work rounds 1 to 6 incl of patt.

**Place Pocket:**

**NOTE:** When instructions read 'Cast off 5 sts, K5' (or other numbers), the st rem on right hand needle after casting off counts as one st.

**Next Round:** P1, (K2, P2) 5 times, 'C4B', K2, P2, K2, P1.

**Next Round:** P1, (K2, P2) 5 times, K6, P2, K2, P1.

**Next Round:** Cast off 16 sts in rib, P1, K2, P2, K6, P2, K2, P1.

**Next Round:** With right side of pocket lining facing and placing inside the pouch, P1, K2, P2, K6, P2, K2, P1 across sts on stitch holder, then P1, K2, P2, K6, P2, K2, P1 ... 32 sts.

Cont working in patt, beg with 11th round, until pouch measures 10 cm from beg.

**Next Round:** P1, \* K2, P2, rep from \* to last 3 sts, K2, P1.

**Next Round:** P1, K2, P2tog, yon (to make a st), K2, P2, K2, yrn (to make a st), P2tog, \* K2, P2, rep from \* to last 3 sts, K2, P1 ... 2 buttonholes.

**Next Round:** P1, \* K2, P2, rep from \* to last 3 sts, K2, P1.

Cast off in rib.

## TO MAKE UP

Unravel cast on ch and pick up sts, placing first 16 sts on one double-pointed needle, and next 15 sts on another double pointed needle.

With a third double-pointed needle in right hand, knit first sts on each needle tog, then knit second sts on each needle tog, and pass first st over second to cast off. Cont in this manner to cast off all sts.

Slip st pocket lining in position. Sew buttons onto inside of pouch to correspond with buttonholes.

If you need help with your pattern or stockist, go to [www.pandayarns.biz](http://www.pandayarns.biz) or phone Australia 613 9380 3888 or Toll Free 1800 337 032 and quote No. Z241



www.pandayarns.biz